


How to control a Quantum or Sprint from a PC


Installation process

First you need to configure your **Bluetooth Network Connection**


1. Right mouse-click the Start - button, then select **Network Connections**
2. Right mouse-click the icon **Bluetooth Network Connection** and choose **Properties**



3. Choose **Internet Protocol Version 4** and click **Properties**



4. Choose **Use the following IP address**




5. For **1080-Sprint** and **Quantum-left machine** manually type in the following setting
IP address 192.168.250.111
Subnet mask 255.255.255.0

For **Quantum-right machine** manually type in the following setting
IP address 192.168.250.222
Subnet mask 255.255.255.0
6. To close click **OK**

Installing the 1080 Software - Windows 10

1. Download the 1080-software from software.1080motion.com Choose install to start the download. When you run the setup, the software will install automatically.
2. Turn on your Quantum or Sprint and be within 0-15m of the machine with your control-device (laptop, tablet, etc.) turned on.
3. Select the Start  - button, then select **Settings** > **Devices** > **Bluetooth**.


4.1 Turn on **Bluetooth** > select the device > **Pair**.



4.2 You can also press + Add a new Bluetooth device and search for your machine that way

How to add a shortcut of the Bluetooth connection

1. Select the **Start** button in the Windows taskbar  > **Control panel/settings**
2. Under **Hardware and Sound/Devices** choose **View devices and printers**



3. Right-click your Quantum or Sprint icon and choose **create shortcut**

User guidelines

Please note, to operate both Quantum machines at the same time you need **two control devices** (computer/computer, computer/tablet etc.) with Bluetooth and 1080 software installed.

All this is pre-installed on the tablets delivered with the Quantum machines

To run in synchro-mode, you also need two control devices running - you can't run it from one computer or laptop alone.

It is possible to operate the left and the right Quantum machine from one device but not at the same time. If you want to run both machines (one at a time) from the same control device, you need to manually change the **Internet Protocol Version 4 IP** to match the left or right Quantum machine.

If you want to use an Apple product as a control device with your Sprint or Quantum, you need a Windows Operating System installed and running on your Apple device

Note that it is very important that you regularly update Windows to the latest available version of your Windows series.

We also strongly recommend you regularly sync your 1080motion software when you have an active internet connection. Failing to do so can result in much valuable data lost if anything should happen to your locally saved files.

It is exactly like when you backup your smartphone etc.